



### **Pacific version 1**

Technolab and Oxyguard are pleased to announce the official release of the Pacific version 1 software. The latest release contains substantial enhancements in performance, reliability, usability and security. The software update includes a new interface, which makes interaction very easy and intuitive.

We have added new super functions to eliminate the human factor and to ensure that you always have absolute control over your facility.

Below is a list of what's new:

- You can set timers and intervals to control relays and I/O units - very useful for creating a feed distribution pattern and control of lighting, pumps, etc.
- Alarm alert by a telephone call. Just in case the person on duty does not reply to the SMS notification informing you about an alarm, the system will make a phone call.
- Email notifications. Alarm notifications can be sent out as emails.
- MA output. New systems have mA outputs for controlling frequency converters or valves.
- New Web Interface. From now on, all Pacific Units are manufactured with Web Interface and you only need to enter the license code to get access.
- Comments Log. You can add notes to the log - keep record of dead fish, feed amount, medicine use, etc.